

Module: apps

Module: apps

Method	Parameters	HTTP Method	Description	URL Example
AIQInstallPath		GET	gets AIQ Install Path	http://localhost:8080/AppvanceServer/rest/apps/AIQInstallPath
AIQStatus		GET	gets AIQ status	http://localhost:8080/AppvanceServer/rest/apps/AIQStatus
ChangePortAndRebootLocalDS3			Modify local ds3 global json with changed port and reboot	
checkLocalDS3Path	String location		Checks the ds3 location is right or wrong	
clearOutput	String type		Clears the required output	
clearOutput	String type		Clears the required output	
exportLogsContent	String logType, int size	GET/ POST	Returns logs data of from requested file	http://localhost:8080/AppvanceServer/rest/apps/exportLogsContent?logType=exportType&size=exportSize
gc		GET/ POST	Init garbage collector, the usage of this should be discouraged and only used if really knows what is being done	http://localhost:8080/AppvanceServer/rest/apps/gc
getDS3			Returns the first Megabyte of the ds3 Server output	http://localhost:8080/AppvanceServer/rest/apps/getDS3
getDS3Size		GET	Returns the DS3 output size	http://localhost:8080/AppvanceServer/rest/apps/getDS3Size

Method	Parameters	HTTP Method	Description	URL Example
getError		GET/ POST	Returns the first Megabyte of the error output	http://localhost:8080/AppvanceServer/rest/apps/getError
getErrorSize		GET/ POST	Returns the error output size	http://localhost:8080/AppvanceServer/rest/apps/getErrorSize
getOutput		GET/ POST	Returns the first Megabyte of console output	http://localhost:8080/AppvanceServer/rest/apps/getOutput
getOutputSize		GET/ POST	Returns the console output size	http://localhost:8080/AppvanceServer/rest/apps/getOutputSize
getOwasp		GET/ POST	Returns the first Megabyte of the OWASP Server output	http://localhost:8080/AppvanceServer/rest/apps/getOwasp
getOwaspSize		GET/ POST	Returns the OWASP output size	http://localhost:8080/AppvanceServer/rest/apps/getOwaspSize
getSahi		GET/ POST	Returns the first Megabyte of the sahi output	http://localhost:8080/AppvanceServer/rest/apps/getSahi
getSahiSize		GET/ POST	Returns the sahi output size	http://localhost:8080/AppvanceServer/rest/apps/getSahiSize
localDS3PortData	String location		read global json to get port data for local ds3	
LRAppium		GET	gets LR/appium Running status	http://localhost:8080/AppvanceServer/rest/apps/LRAppium
LRAppiumInstalledPath		GET	gets LR/appium installed path	http://localhost:8080/AppvanceServer/rest/apps/LRAppiumInstalledPath
ping		GET/ POST	calling this method will return the word "running" if AIQ is running.	http://localhost:8080/AppvanceServer/rest/apps/ping
reboot		GET/ POST	Reboots AIQ	http://localhost:8080/AppvanceServer/rest/apps/reboot
restartDS3Server		GET/ POST	Stops and Starts up the test Designer Server	http://localhost:8080/AppvanceServer/rest/apps/restartDS3Server

Method	Parameters	HTTP Method	Description	URL Example
setSahiBrowserConfig	String content	GET/ POST	Sets the Sahi browser (legacy) configuration running under localhost	http://localhost:8080/AppvanceServer/rest/apps/setSahiBrowserConfig?content=//please see below content format for this string
shutdown		GET/ POST	Shuts down Appvance IQ.	http://localhost:8080/AppvanceServer/rest/apps/shutdown
testNodePermission		GET	testnode permissions	http://localhost:8080/AppvanceServer/rest/apps/testNodePermission
updateCertificate	String domain		updates Appvance certificate and reboots	

Revision #1
Created 2026-07-24 14:30:37 UTC by Admin
Updated 2026-07-24 14:30:37 UTC by Admin